
## How to edit block attributes in Microsoft Excel?

1114 kbadmin April 3, 2016 Tips & Tricks 0 5051

Block attributes is a great way to store information but if you already have many blocks in your drawing, editing the attributes can be tedious and prone to error. It would be easier to edit the attributes in table, isn"t it?



**Export the attributes data (ATTOUT)** 


You can edit the attributes in Microsoft Excel. To do that, first you need to export the data from GstarCAD. You can use ATTOUT command. Or you can access it in Express Tools tab> Blocks panel. Export attributes will ask you to define a file name (in .txt format) and select objects to export.

		out View Mana Change Reset Dimension Text Text View Driver Noview Duck Information		Help 5 % * 8 8 0	Blocks Text Too Dimensis Selection Modify Draw Tools Table To	in Tools		Copy Nested Objects(C) Explode Attributes to Test Export Attribute Information Import Attribute Information Stat. Blocks Number
Enter output f			- 01	P -	×	Fools(C) 34s	•	Change Block Color(Y) Change Block Linewidth Change Block Test Angle()
Desktop Libraries	Name authorpalette color lcons MenuFiles toolpalette	Date modified 7/1/2013 2:30 Pizzak 7/1/2013 2:30 Pizzak 7/1/2013 2:30 Pizzak 7/1/2013 2:30 Pizzak 7/1/2013 2:30 Pizzak	Type File folder File folder File folder File folder File folder	Sat		* 	14 14 14 14 14 14 14 14 14 14 14 14 14 1	List Xref/Block Properties Trim to Nested Objects
Network		or plant drawing st/Template/Extract File(*)		1	Save Cancel			

## **Editing the attributes**

You can edit the file using notepad. But it may not be convenient. It would be more convenient to edit it in Microsoft Excel. Furthermore, you can use formula if the attribute should be calculated value. You can open txt file in Excel and edit there.

Open Microsoft Excel, then open file. Change the file type to Text Files or All Files to see your exported file.



Click open. You will see import wizard. You can click Next to review the import settings. Or just click finish to accept default settings. Usually default settings would be fine. Now you can edit the values.

DO NOT edit the handle column. It's the block ID. If you change it, it might not be imported properly.

	A	В	C	D	E	F	G
1	HANDLE	BLOCKNA	REF	MAKE/MC	SIZE	TYPE	SERVICE
2	'8B10	AMB006	R1	HOLYOAK	150X150	CEILING MOUNTED	EXHAUST
3	'8AFD	AMB006	R1	HOLYOAK	150X150	CEILING MOUNTED	EXHAUST
4	'8AE2	AMB006	R2	HOLYOAK	200X200	WALL MOUNTED	INHAUST
5	'8ACF	AMB006	R1	HOLYOAK	150X150	CEILING MOUNTED	EXHAUST
6	'8AA9	AMB006	R1	HOLYOAK	150X150	CEILING MOUNTED	EXHAUST
7	'8A96	AMB006	R1	HOLYOAK	150X150	CEILING MOUNTED	EXHAUST
8	'8A83	AMB006	R1	HOLYOAK	150X150	CEILING MOUNTED	EXHAUST
9	'8A70	AMB006	R1	HOLYOAK	150X150	CEILING MOUNTED	EXHAUST
10	'8A5D	AMB006	R1	HOLYOAK	150X150	CEILING MOUNTED	EXHAUST
11	'8A56	AMB006	R2	HOLYOAK	200X200	WALL MOUNTED	INHAUST

After you finished, save the file. You may see warning because you are working in txt format. Just click yes, because we want to keep it in that format.

## Import the attributes data (ATTIN)

You might already guess the next step. Yes, you can import the value after finish editing.

You can use import attributes or ATTIN command. Or you can access it in Express Tools tab> Blocks panel.

Command: ATTIN

Reading the input file... Done. 11 Block inserts modified.

This is very handy if you work with many blocks in your drawing. Editing block attributes in drawing would take a lot of time.

	Cesktop	- 0	🗊 🔛 🖬 🖬 🕶	
(E.	Name	Size	Item type	
ecent Places	Computer Computer Computer Computer Cockies - Shortcut Floor plant drawing		2 KB Shortcut 21 KB Text Document	
1				
Computer () Network	File game: Floor plant Files of type: Tot files (* tot		Qpen     Cancel	

Online URL: https://www.kb2.gstarcad.com.my/article.php?id=1114