GstarCAD dongle upgrade for standalone version

1271 kbadmin June 30, 2021 Update and Upgrade 0 3532

For the **standalone dongle** version newer than **GstarCAD 2012**, just installed the latest GstarCAD and followed these steps below to upgrade your dongle to activate the latest GstarCAD.

1. Insert a **dongle into the USB port** of your computer.

2. Booting **GstarCAD**, Click **Dongle Upgrade** (U), and select a **version of GstarCAD** (Professional, Standard, and Academic).

GstarCAD License Activation		- ×
License Key(L)	Please follow the steps below to upgrade your standalone dongle. 1. <u>GENERATE</u> LOV file	
USB Dongle(D)	 Send LOV file to your local distributor / reseller from whom you purchased Gstan LIV file 	CAD products and get
Network Dongle(T)	3. LOAD LIV file and click Upgrade button	
Standalone Dongle(S)		
Dongle Upgrade(U) 4		Upgrade
Product Version:		
Professional Standard		
• Academic	Back(K)	Exit(E)

3. Click the **GENERATE** button to get the **LOV** file, and then save it to the local computer.



4. Send the **LOV file** to your local distributor/reseller from whom you purchased the GstarCAD product upgrade and get the LIV file.

5. Click **LOAD** to load the **LIV file** and click the Upgrade button to upgrade your dongle.

GstarCAD License Activation		- ×
License Key(L)	Please follow the steps below to upgrade your standalone dongle. 1. GENERATE LOV file	
USB Dongle(D)	 Send LOV file to your local distributor / reseller from whom you purchased GstarCAD products LIV file 	and get
Network Dongle(T)	3. LOAD LIV file and click Upgrade button	
Standalone Dongle(S)	C:/Users\Desktop/2017-04011102.lv	
Dongle Upgrade(U)		Ipgrade
Product Version:		
Professional		
Standard		
Academic	Back(K) Exit	(E)

No matter how you activate your GstarCAD, when you finish activating, the GstarCAD License Activation wizard quits out. Instead, the system will prompt you: Please restart your software to finish the activation process.

GstarCAD License Manager			- ×		
		formation			
	License information				
	License Type: License Key: Product Version: Language: Expiration date:	Standalone USB Dongle GstarCAD 2020 Professiona ENG 09-Sep-2020			
6* A		rate(A)	C Return(R)		

You can click **Help** menu - **Register** to see whether you really activate your software; you can see the following picture to ensure you finish activating GstarCAD.

If your standalone dongle version is from **GstarCAD 2003 to 2011** and you just installed the latest GstarCAD software, you can follow these steps below to upgrade your dongle to activate GstarCAD.

1. Insert a **dongle into the USB port** of your computer.

2. Booting **GstarCAD**, Click **Dongle Upgrade** (U), and select a **version of GstarCAD** (Professional, Standard, and Academic).

3. Send the **Product Number** to your local distributor/reseller from whom you purchased GstarCAD products, and then you will get the Serial Number and Upgrade Code.

GstarCAD License Activation		- ×
License Key(L)	Please follow the steps below to upgrade your standalone dongle.	
USB Dongle(D)	GENERATE LOV file Send LOV file to your local distributor / reseller from whom you purchased GstarCAD products LIV file	and get
Standalone Dongle(S)	3. LOAD LIV file and click Upgrade button	
Network Dongle(T) Dongle Upgrade(U)		pgrade
	Upgrade your dongle(2003-2011) via codes. Please send the Product Number to us, Serial Number and Upgrade Code will be sent to you for upgrading your dongle.	
	Product Number	
	Serial Number	
Product Version: • Professional		Ipgrade
Standard Academic	Back(K) Exit	(E)

4. Please input **Serial Number** and **Upgrade Code**, then click the **Upgrade** button to finish dongle upgrading.

Online URL: <u>https://www.kb2.gstarcad.com.my/article.php?id=1271</u>